GTK+ for OpenVMS Alpha

Release Notes

July 31, 2000

Introduction

GTK+ *Version 1.2.8 for OpenVMS Alpha* is an open source, free software library for creating graphical user interfaces. It is an unofficial, interim port of GTK+. See <u>http://www.openvms.compaq.com/openvms/products/ips/gtk.html</u> for information on reporting problems in *GTK*+ *for OpenVMS*.

See http://www.gtk.org for more information about GTK+.

Prerequisites

GTK+ *for OpenVMS* requires the following software. (Other configurations have not been tested.)

- OpenVMS Alpha Version 7.1-2
- Compaq C Version 6.2-006
- The OpenVMS Porting Library must be installed, and:
 - the Porting Library shareable image must be accessible via the VMS_JACKETS logical name
 - the Porting Library header files must be accessible (edit VMS_BUILD_SETUP.COM)
- Perl 5.002_01 or higher (optional)
- GNU AWK 2.15 (patchlevel 6) (optional)

Note: Perl and AWK are used in a full build, but you can modify the OpenVMS GTK+ build procedures so that neither of these utilities is required.

GTK+ for OpenVMS is built in DCL using OpenVMS-specific build procedures. The UNIX tools make and autoconf (configure) are **not** required.

Expanding and Installing GTK+ for OpenVMS

Perform the following steps to expand and install *GTK*+ *for OpenVMS*.

Note: You must also download and install the OpenVMS Porting Library in order to use *GTK*+ *for OpenVMS*.

Download GTK+ for OpenVMS.

A self-extracting archive and a .ZIP file are available for download. The contents of the kits are identical.

Download the self-extracting archive to expand and install the kit on an Alpha system. You can expand the .ZIP file on an Alpha system or on a PC, if you want to simply view the files in the kit.

After you download the kit, create a directory where you want the source code tree to reside. Set your default directory to that location.

\$ CREATE/DIRECTORY DKA0:[GTK128] \$ SET DEFAULT DKA0:[GTK128]

To expand and install the GTK+ for OpenVMS self-extracting archive, run the kit you downloaded. For example:

\$ RUN DKA0:[KITS]GTK128-OPENVMS-A1.SFX_AXPEXE

Building GTK+ for OpenVMS

This section explains how to build *GTK*+ for *OpenVMS*.

Edit [GTK128]VMS_BUILD_SETUP.COM to match your system's configuration.

If you do *not* have Perl or AWK, edit [GTK128.GTK.GTK]VMS_BUILD.COM and uncomment the goto no_perl statement.

The OpenVMS kit contains pre-built generated files. You should rebuild GTK.DEFS and the other generated files only if you are making changes to GTK+ source code.

(Optional) If you need to build a debug version of GTK+, enter the following command:

\$ DEFINE BUILD_DEBUG 1

Run VMS_BUILD.COM from the top-level directory:

```
$ SET DEFAULT [GTK128]
$ @VMS_BUILD
```

Depending upon how fast your system is, the build will take between 10-30 minutes. A few warnings are normal.

During a build of GTK+ for OpenVMS, the following directories are built:

- glib
 - gmodule
 - gthread
 - tests (optional)
- gtk
 - gdk
 - gtk

Each directory contains a VMS_BUILD.COM that is used to build the contents of that directory, plus the contents of its subdirectories.

Most tests can be built by invoking VMS_BUILD.COM in the appropriate directory and passing it the parameter test.

After the build has completed, four shareable images have been created:

- [GTK128.GLIB]LIBGLIB.EXE
- [GTK128.GLIB.GMODULE]LIBGMODULE.EXE
- [GTK128.GTK.GDK]LIBGDK.EXE
- [GTK128.GTK.GTK]LIBGTK.EXE

Your Application and GTK+ for OpenVMS

Consider the following when you build your application and link against the GTK+ shareable images.

• The code added to *GTK+ for OpenVMS* uses event flags 2 and 3 without allocating them. **Your application must not use these event flags.** This restriction will be lifted in GTK+ 1.3 by ensuring that any event flags used are

allocated via LIB\$GET_EF.

- GTK+ is compiled using /NAMES=AS_IS. This means that all of the entry points in the shareable images are case-sensitive, and you will have to compile your application the same way. If you want to change this, edit VMS_CC.COM (to remove NAMES=AS_IS) and all the xxx_create.opt files (to remove the CASE_SENSITIVE statements) and rebuilt GTK+.
- GTK+ is compiled using /NAMES=SHORTEN. This means that any long symbol names in the GTK code are shortened rather than truncated. Your application should also be compiled with this qualifier.
- GTK+ is compiled using /FLOAT=IEEE and /IEEE=DENORM. Your application must also be built with these qualifiers.
- When compiling code that uses GLib, include the following directories on your header file include path:
 - [GTK128.GLIB]
 - [GTK128.GLIB.GMODULE]
- When compiling code that uses GTK, include the following directories on your header file include path:
 - [GTK128.GTK]
 - [GTK128.GLIB]
 - [GTK128.GLIB.GMODULE]
- There are four shareable images against which you need to link your application, as follows:
 - [GTK128.GLIB]LIBGLIB.EXE
 - [GTK128.GLIB.GMODULE]LIBGMODULE.EXE
 - [GTK128.GTK.GDK]LIBGDK.EXE
 - [GTK128.GTK.GTK]LIBGTK.EXE

POSIX and GNV Considerations

If you are building your application inside of POSIX or GNV, then GLib and GTK both need to be *installed* so that autoconf based applications can locate the installations. If

you have built GLib and GTK on OpenVMS, then they are already installed and glibconfig and gtk-config can be used as usual.

For example, if your GTK+ directory root is DKB300:[GTK128], you can configure an autoconf based application as follows:

```
configure \
    --with-glib --with-glib-prefix=/dkb300/gtk128/glib/ \
    --with-gtk --with-gtk-prefix=/dkb300/gtk128/gtk/
```

Source File Changes

Following is a summary of the changes made to the GTK+ source files.

glib

- [GTK128.GLIB]GMAIN.C
 - Changed to use event flags as the wakeup mechanism

gtk

- [GTK128.GTK.GDK]GDKDND.C
 - Use VMS_SETUP_WINDOW_NOTIFICATION macro when a window is created
- [GTK128.GTK.GDK]GDKEVENTS.C
 - Add code to translate OpenVMS-specific MOTIF key bindings so they appear normal
 - Use an event flag (VMS_EF_GTK_WINDOW_EVENT) for notification instead of ConnectionNumber
- [GTK128.GTK.GDK]GDKWINDOW.C
 - Use VMS_SETUP_WINDOW_NOTIFICATION macro when a window is created
- [GTK128.GTK.GDK]GXID.C
 - Change name of socket_fd (this file is not built)
- [GTK128.GTK.GTK]GTKDND.C
 - Add stdlib.h so that abs is known

- [GTK128.GTK.GTK]GTKFILESEL.H
 - Use macros to copy/compare struct st_ino fields
 - Make a local inode definition inode[3]
 - Perform case blind comparisons
 - Change find_parent_dir_fullname so that it does not use chdir (cannot chdir up to /)
- [GTK128.GTK.GTK]GTKMAIN.C
 - Translate HOME to UNIX equivalent and re-save
 - Include unixlib.h
- [GTK128.GTK.GTK]TESTRGB.C
 - ifdef out struct timezone declaration and make second arg in gettimeofday call NULL instead of tz

Build Files Included in GTK+ for OpenVMS

Compaq provides the following OpenVMS-specific build files in the GTK+ kit.

File	Description
[GTK128]VMS_CC.COM	Command file to compile a single C file
[GTK128]VMS_SHARE.COM	Command file to create a shareable image
[GTK128]VMS_LINK.COM	Command file to create an executable image
[GTK128]VMS_BUILD_SETUP.C OM	Common setup file invoked by each vms_build.com
[GTK128]VMS_BUILD.COM	Command file for building on OpenVMS
[GTK128.GLIB]CONFIG.H_VMS	Prebuilt OpenVMS version of config.h
[GTK128.GLIB]GLIBCONFIG.H_ VMS	Prebuilt OpenVMS version of glibconfig.h
[GTK128.GLIB]LIBGLIB_VMS.OI T	PLinker options file to pull in libglib

[GTK128.GLIB]LIBGLIB_CREATELinker options file to create libglib shareable image _VMS.OPT

[GTK128.GLIB]VMS_BUILD.CO Command file for building on OpenVMS M

[GTK128.GLIB]VMS GLIB-Command file to create glib-config config.com [GTK128.GLIB.GMODULE] Prebuilt OpenVMS version of gmoduleconf.h GMODULECONF.H_VMS Linker options file to pull in libgmodule [GTK128.GLIB.GMODULE] LIBGMODULE_VMS.OPT [GTK128.GLIB.GMODULE] Linker options file to create libgmodule shareable image LIBGMODULE CREATE VMS.O PT [GTK128.GLIB.GMODULE]VMS Command file for building on OpenVMS BUILD.COM [GTK128.GLIB.GTHREAD]VMS_ Command file for building on OpenVMS BUILD.COM [GTK128.GLIB.TESTS]VMS BUILCommand file for building on OpenVMS D.COM

[GTK128.GTK]CONFIG.H_VMS Prebuilt OpenVMS version of config.h

[GTK128.GTK]VMS_BUILD.COMCommand file for building on OpenVMS

[GTK128.GTK]VMS_GTK- Command file to create gtk-config config.com

[GTK128.GTK.GDK]LIBGDK_VMLinker options file to pull in libgdk S.OPT

[GTK128.GTK.GDK] Linker options file to create libgdk shareable image LIBGDK_CREATE_VMS.OPT

[GTK128.GTK.GDK]VMS_BUILD Command file for building on OpenVMS .COM

[GTK128.GTK.GTK]LIBGTK_VM Linker options file to pull in libgtk S.OPT

[GTK128.GTK.GTK] Linker options file to create libgtk shareable image LIBGTK_CREATE_VMS.OPT

[GTK128.GTK.GTK]VMS_BUILD. Command file for building on OpenVMS COM

[GTK128.GTK.PO]VMS_BUILD.CCommand file for building on OpenVMS OM

Distribution restrictions and disclaimer

Customer agrees that he/she is not prohibited by the U.S. or other government export control regulations from receiving this software or technical data.

Copyright and trademark information

Compaq believes the information in this document is accurate as of its publication date; such information is subject to change without notice.

Copyright Compaq Computer Corporation 2000. All rights reserved.

Compaq, the Compaq logo, and the DIGITAL logo are registered in the U.S. Patent and Trademark Office. Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. Microsoft, Windows, and Windows 95 are registered trademarks, and NT and Windows NT are trademarks, of Microsoft Corporation.

Alpha, AlphaServer, AlphaStation, DEC, DIGITAL, OpenVMS, Tru64, VAX, and VMS are trademarks of Compaq Computer Corporation.